

```

classdef CascadeObjectDetector < matlab.System
    %CascadeObjectDetector Detect objects using the Viola-Jones algorithm
    % DETECTOR = vision.CascadeObjectDetector creates a System object
    % that detects objects using the Viola-Jones algorithm. The DETECTOR
    % is capable of detecting a variety of objects, including faces and a
    % person's upper body. The type of object to detect is controlled by
    % the ClassificationModel property. By default, the DETECTOR is
    % configured to detect faces.
    %
    % DETECTOR = vision.CascadeObjectDetector(MODEL) creates a System
    % object, DETECTOR, configured to detect objects defined by MODEL.
    % MODEL is a string describing the type of object to detect. There
    % are several valid MODEL strings. Examples include
    % 'FrontalFaceCART', 'UpperBody', and 'ProfileFace'.
    %
    % <a href="matlab:helpview(fullfile(docroot,'toolbox','vision','vision
map'),'vision.CascadeObjectDetector.ClassificationModel')">A list of all available
models is shown in the documentation.</a>
    %
    % DETECTOR = vision.CascadeObjectDetector(XMLFILE) creates a System
    % object, DETECTOR, and configures it to use the custom classification
    % model specified with the XMLFILE input. XMLFILE can be created using
    % the trainCascadeObjectDetector function or OpenCV training
    % functionality. You must specify a full or relative path to the
    % XMLFILE, if it is not on the MATLAB path.
    %
    % DETECTOR = vision.CascadeObjectDetector(...,Name,Value) configures
    % the System object properties, specified as one or more name-value
    % pair arguments. Unspecified properties have default values.
    %
    % BBOXES = step(DETECTOR, I) performs multi-scale object detection on
    % the input image, I, and returns, BBOXES, an M-by-4 matrix defining
    % M bounding boxes containing the detected objects. Each row in
    % BBOXES is a four-element vector, [x y width height], that specifies
    % the upper left corner and size of a bounding box in pixels. When no
    % objects are detected, BBOXES is empty. I must be a grayscale or
    % truecolor (RGB) image.
    %
    % [...] = step(DETECTOR, I, ROI) detects objects within the
    % rectangular search region specified by ROI. ROI must be a 4-element
    % vector, [x y width height], that defines a rectangular region of
    % interest within image I. The 'UseROI' property must be true to use
    % this syntax.
    %
    % CascadeObjectDetector methods:
    %
    % step      - See above description for use of this method
    % release   - Allow property value and input characteristics changes
    % clone     - Create cascade object detector object with same property
    %             values
    % isLocked  - Locked status (logical)
    %
    % CascadeObjectDetector properties:
    %
    % ClassificationModel - Name of the classification model

```

```

%   MinSize           - Size of the smallest object to detect
%   MaxSize           - Size of the biggest object to detect
%   ScaleFactor        - Scaling for multi-scale object
%                       detection
%   MergeThreshold     - Threshold for merging colocated detections
%   UseROI             - Detect objects within a region of interest
%
%   % Example 1: Face detection
%   % -----
%   faceDetector = vision.CascadeObjectDetector; % Default: finds faces
%
%   I = imread('visionteam.jpg');
%   bboxes = step(faceDetector, I); % Detect faces
%
%   % Annotate detected faces
%   IFaces = insertObjectAnnotation(I, 'rectangle', bboxes, 'Face');
%   figure, imshow(IFaces), title('Detected faces');
%
%   % Example 2: Upper body detection
%   % -----
%   bodyDetector = vision.CascadeObjectDetector('UpperBody');
%   bodyDetector.MinSize = [60 60];
%   bodyDetector.MergeThreshold = 10;
%   bodyDetector.UseROI = true;
%
%   I2 = imread('visionteam.jpg');
%
%   % Search for objects in the top half of the image.
%   [height, width, ~] = size(I2);
%   roi = [1 1 width height/2];
%   bboxBody = step(bodyDetector, I2, roi); % Detect upper bodies
%
%   % Annotate detected upper bodies
%   IBody = insertObjectAnnotation(I2, 'rectangle', ...
%                                   bboxBody, 'Upper Body');
%   figure, imshow(IBody), title('Detected upper bodies');
%
%   See also trainCascadeObjectDetector, vision.PeopleDetector
%
%   Copyright 2011-2015 The MathWorks, Inc.
%
%   References:
%   -----
%   [1] Paul Viola and Michael J. Jones "Rapid Object Detection using a
%       Boosted Cascade of Simple Features" IEEE CVPR, 2001
%
%   [2] Rainer Lienhart, Alexander Kuranov, Vadim Pisarevsky
%       "Empirical Analysis of Detection Cascades of Boosted Classifiers
%       for Rapid Object Detection", DAGM Symposium for Pattern
%       Recognition, pp. 297-304, 2003
%
%#codegen
%#ok<*EMCLS>
%#ok<*EMCA>
    properties(Nontunable)

```

```

%ClassificationModel A trained cascade classification model
% Specify the name of the model as a string. The value specified
% for this property may be one of the valid MODEL strings listed
% <a href="matlab:helpview(fullfile(docroot,'toolbox','vision','vision.
map'),'vision.CascadeObjectDetector.ClassificationModel')">here</a> or an OpenCV XML
file containing custom classification
% model data. When an XML file is specified, a full or relative
% path is required if the file is not on the MATLAB path.
%
% Default: 'FrontalFaceCART'
%
% See also <a href="matlab:helpview(fullfile
(docroot,'toolbox','vision','vision.map'),'vision.CascadeObjectDetector
ClassificationModel')">Available models</a>
ClassificationModel = 'FrontalFaceCART';
end
properties
%MinSize Size of the smallest object to detect
% Specify the size of the smallest object to detect, in pixels,
% as a two-element vector, [height width]. Use this property to
% reduce computation time when the minimum object size is known
% prior to processing the image. When this property is not
% specified, the minimum detectable object size is the image size
% used to train the classification model. This property is
% tunable.
%
% Default: []
MinSize = [];
%MaxSize Size of the biggest object to detect
% Specify the size of the biggest object to detect, in pixels, as
% a two-element vector, [height width]. Use this property to
% reduce computation time when the maximum object size is known
% prior to processing the image. When this property is not
% specified, the maximum detectable object size is SIZE(I). When
% 'UseROI' is true, the maximum detectable object size is the
% defined by the height and width of the ROI. This property is
% tunable.
%
% Default: []
MaxSize = [];
%ScaleFactor Scaling for multi-scale object detection
% Specify the factor used to incrementally scale the detection
% scale between MinSize and MaxSize. The ScaleFactor must be
% greater than or equal to 1.0001. At each increment, N, the
% detection scale is
%
% round(TrainingSize*(ScaleFactor^N))
%
% where TrainingSize is the image size used to train the
% classification model. The training size used for each
% classification model is shown <a href="matlab:helpview(fullfile
(docroot,'toolbox','vision','vision.map'),'vision.CascadeObjectDetector
ClassificationModel')">here</a>. This property is tunable.
%
% Default: 1.1

```

```

    ScaleFactor = 1.1;
    %MergeThreshold Threshold for merging colocated detections
    % Specify a threshold value as a scalar integer. This property
    % defines the minimum number of colocated detections needed to
    % declare a final detection. Groups of colocated detections that
    % meet the threshold are merged to produce one bounding box
    % around the target object. Increasing this threshold can help
    % suppress false detections by requiring that the target object
    % be detected multiple times during the multi-resolution
    % detection phase. By setting this property to 0, all detections
    % are returned without merging. This property is tunable.
    %
    % Default: 4
    MergeThreshold = 4;
end

properties(Nontunable, Logical)
    % UseROI Detect objects within a ROI
    % Set to true to detect objects within a rectangular region of
    % interest within I.
    %
    % Default: false
    UseROI = false;
end

properties (Transient, Access = private)
    pCascadeClassifier; % OpenCV pCascadeClassifier
end

properties(Hidden, Dependent, SetAccess = private)
    %TrainingSize Image size used to train classification model
    % This is the smallest object that the classification model is
    % trained to detect. It is the smallest object size that the
    % model can detect.
    TrainingSize;
end
methods
    %-----
    % Constructor
    %-----
    function obj = CascadeObjectDetector(varargin)
        if (isSimMode())
            obj.pCascadeClassifier = vision.internal.CascadeClassifier;
        else
            obj.pCascadeClassifier = ...
                vision.internal.buildable.cascadeClassifierBuildable;
        end
        cascadeClassifier_construct();
    end
    setProperties(obj, nargin, varargin{:}, 'ClassificationModel');
    % we need to load XML before calling getClassifierInfo (called
    % from obj.TrainingSize in validatePropertiesImpl
    loadXMLFromClassModel(obj);
    validatePropertiesImpl(obj);
end

```

```

%-----
% ClassificationModel set method
%-----
function set.ClassificationModel(obj,value)
    coder.extrinsic('exist');

    validateattributes(value,{ 'char'},{ 'nonempty','row'},↵
'CascadeObjectDetector');

    % for exist: file must be in path or an absolute path must
    % be provided
    file_exists = coder.internal.const(exist(value,'file')) == 2;
    coder.internal.errorIf(~isSupportedModel(value) && ~file_exists,...
        'vision:ObjectDetector:modelNotFound',value);

    obj.ClassificationModel = value;
    loadXMLFromClassModel(obj);
end

%-----
% UseROI set method
%-----
function set.UseROI(obj, value)
    obj.UseROI = logical(value);
end

%-----
% ScaleFactor set method
%-----
function set.ScaleFactor(obj,value)
    validateattributes( value,{ 'numeric'},...
        { 'scalar', '>=',1.0001,'real', 'nonempty','nonsparse','finite'},...
        '', 'ScaleFactor');
    obj.ScaleFactor = value;
end

%-----
% MinSize set method
%-----
function set.MinSize(obj,value)
    validateSize('MinSize',value);
    obj.MinSize = value;
end

%-----
% MaxSize set method
%-----
function set.MaxSize(obj,value)
    validateSize('MaxSize',value);
    obj.MaxSize = value;
end

%-----
% MergeThreshold set method
%-----

```

```

function set.MergeThreshold(obj,value)
    validateattributes( value, ...
        {'numeric'}, {'scalar','>=' 0, 'real','integer',...
            'nonempty','nonsparse','finite'},...
        '', 'MergeThreshold');
    obj.MergeThreshold = value;
end

%-----
% TrainingSize get method
%-----
function value = get.TrainingSize(obj)
    if (isSimMode())
        info = obj.pCascadeClassifier.getClassifierInfo();
        value = info.originalWindowSize;
    else
        [originalWindowSize, ~]=vision.internal.buildable✓
cascadeClassifierBuildable.cascadeClassifier_getClassifierInfo(..
        obj.pCascadeClassifier);
        value = originalWindowSize;
    end
end
end

methods(Access = protected)
%-----
% Cross validate properties
%-----
function validatePropertiesImpl(obj)

    % validate that MinSize is greater than or equal to the minimum
    % object size used to train the classification model

    if ~isempty(obj.MinSize)
        % obj.TrainingSize calls getClassifierInfo in get.TrainingSize
        coder.internal.errorIf(any(obj.MinSize < obj.TrainingSize),...
            'vision:ObjectDetector:minSizeLTTrainingSize',...
            obj.TrainingSize(1),obj.TrainingSize(2));
    end

    % validate the MaxSize is greater than the
    % pModel.TrainingSize when MinSize is not specified
    if isempty(obj.MinSize) && ~isempty(obj.MaxSize)
        % obj.TrainingSize calls getClassifierInfo in get.TrainingSize
        coder.internal.errorIf(any(obj.TrainingSize >= obj.MaxSize),...
            'vision:ObjectDetector:modelMinSizeGTMaxSize',...
            obj.TrainingSize(1),obj.TrainingSize(2));
    end

    % validate that MinSize < MaxSize
    if ~isempty(obj.MaxSize) && ~isempty(obj.MinSize)
        coder.internal.errorIf(any(obj.MinSize >= obj.MaxSize),...
            'vision:ObjectDetector:minSizeGTMaxSize');
    end
end

```

```

end

%-----
% Validate inputs to STEP method
%-----
function validateInputsImpl(obj,I,varargin)
    validateattributes(I,...
        {'uint8','uint16','double','single','int16'},...
        {'real','nonsparse'},...
        '','',2);
    coder.internal.errorIf(~any(ndims(I)==[2 3]),...
        'vision:dims:imageNot2DorRGB');

    sz = size(I);
    coder.internal.errorIf(ndims(I)==3 && sz(3) ~= 3,...
        'vision:dims:imageNot2DorRGB');

    if obj.UseROI
        vision.internal.detector.checkROI(varargin{1},size(I));
    end
end

%-----
% STEP method implementation
%-----
function bboxes = stepImpl(obj,I,varargin)

    if obj.UseROI
        roi = varargin{1};
    else
        roi = zeros(0,4);
    end

    Iroi = vision.internal.detector.cropImageIfRequested(I, roi, obj.UseROI);

    Iu8 = im2uint8(Iroi);

    grayImage = convertToGrayscale(obj, Iu8);

    if (isSimMode())

        bboxes = double(obj.pCascadeClassifier.detectMultiScale(grayImage,...
            double(obj.ScaleFactor),...
            uint32(obj.MergeThreshold),...
            int32(obj.MinSize),...
            int32(obj.MaxSize)));
    else

        % OpenCV library works on transposed data
        Iu8_grayT = grayImage';

        if isempty(obj.MinSize)
            obj_MinSize = [0 0];
        else
            obj_MinSize = obj.MinSize;
        end
    end
end

```

```

        end
        if isempty(obj.MaxSize)
            obj_MaxSize = [0 0];
        else
            obj_MaxSize = obj.MaxSize;
        end
        bboxes = vision.internal.buildable.cascadeClassifierBuildable
cascadeClassifier_detectMultiScale(obj.pCascadeClassifier ,...
    Iu8_grayT, ...
    double(obj.ScaleFactor), ...
    uint32(obj.MergeThreshold), ...
    int32(obj_MinSize), ...
    int32(obj_MaxSize));
    end

    bboxes(:,1:2) = vision.internal.detector.addOffsetForROI(bboxes(:,1:2))
roi, obj.UseROI);

end

%-----
% Release method implementation
%-----
function releaseImpl(obj)
    if ~isSimMode()
        % delete cascadeClassifier object
        vision.internal.buildable.cascadeClassifierBuildable
cascadeClassifier_deleteObj(obj.pCascadeClassifier);
    end
end

%-----
% Custom save/load method
%-----
function s = saveObjectImpl(obj)
    s = saveObjectImpl@matlab.System(obj);
end

function loadObjectImpl(obj,s, ~)

    coder.extrinsic('exist');

    obj.ScaleFactor = s.ScaleFactor;
    obj.MinSize = s.MinSize;
    obj.MaxSize = s.MaxSize;
    obj.MergeThreshold = s.MergeThreshold;

    invalidModel = false;
    if isfield(s,'ClassificationModel') && ischar(s.ClassificationModel)
        if (~isSupportedModel(s.ClassificationModel))

            file_exists = coder.internal.const(exist(s
ClassificationModel,'file')) == 2;
            if (~file_exists)
                invalidModel = true;

```



```

        % error while setting the ClassificationModel
        % throw a warning and leave ClassificationModel set to default
        warning(...
            message('vision:ObjectDetector:modelNotFoundOnLoad',...
                s.ClassificationModel,'FrontalFaceCART'));
    end
end

if (~invalidModel)
    obj.ClassificationModel = s.ClassificationModel;
end

if isfield(s, 'UseROI') % UseROI added in R2015a
    obj.UseROI = s.UseROI;
else
    obj.UseROI = false;
end

end

%-----
% Initialize classification model
%-----
function loadXMLFromClassModel(obj)
    if (isSimMode())
        obj.pCascadeClassifier.load(obj.getModelPath(obj)
ClassificationModel));
    else
        % append char(0) to get a Null-terminated string.
        ClassificationModelPath = coder.internal.const([obj.getModelPath(obj)
ClassificationModel) char(0)]);
        vision.internal.buildable.cascadeClassifierBuildable
cascadeClassifier_load(...
            obj.pCascadeClassifier, ClassificationModelPath);
        % for packNGo, we need to put the model file in the zip
        % folder. 'load' function first looks for the model file in
        % the original path, if it is not found there, it searches
        % for the file in the current folder.
        coder.updateBuildInfo('addNonBuildFiles',
ClassificationModelPath, '', 'BlockModules');
    end
end

%-----
% Return the number of inputs
%-----
function num_inputs = getNumInputsImpl(obj)
    if obj.UseROI
        num_inputs = 2;
    else
        num_inputs = 1;
    end
end

%-----

```

```

% Return the number of outputs
%-----
function num_outputs = getNumOutputsImpl(~)
    num_outputs = 1;
end
end

methods(Access = private, Hidden)
%-----
% Converts RGB to grayscale if needed.
%-----
function grayImage = convertToGrayscale(~, Iu8)
    if ndims(Iu8) == 3
        if isempty(Iu8)
            % color space converter does not allow empty.
            grayImage = Iu8(:, :, 1);
        else
            grayImage = rgb2gray(Iu8);
        end
    else
        grayImage = Iu8;
    end
end
end

methods(Static, Hidden)
%-----
% getModelPath returns full path to model data file
%-----
function file_path = getModelPath(name)
    coder.extrinsic('ctfroot');
    coder.extrinsic('matlabroot');
    coder.extrinsic('fullfile');
    coder.extrinsic('which');

    if isdeployed && isSimMode()
        rootDirectory = coder.internal.const(ctfroot);
    else
        rootDirectory = coder.internal.const(matlabroot);
    end

    dataDirectory = coder.internal.const(fullfile(
(rootDirectory, 'toolbox', 'vision', ...
    'visionutilities', 'classifierdata', 'cascade')));

    % Get the path to the model data file so that the data can be
    % loaded using OpenCV

    [isSupportedMdl, filename] = getFileName(name);
    if isSupportedMdl
        %filename = getFileName(name);
        if strncmp(filename, 'lbp', 3)
            feature_type = 'lbp';
        else
            feature_type = 'haar';

```

```

        end
        % construct full path to file
        file_path = coder.internal.const(fullfile(dataDirectory,feature_type,
filename));
    else
        % custom file supplied; 3 options:
        % just file name which is on the path: use which to get full path
        % file name with relative or absolute path: just use user's input

        % determine if it is on the path
        file_fullPath = coder.internal.const(which(name));
        if isempty(file_fullPath) % not on the path nor in current directory
            file_path = coder.internal.const(name); % must be full/relative
path
        else
            file_path = file_fullPath;
        end
    end
end
end
end
end % of classdef

%-----
% Validation for MinSize and MaxSize
%-----
function validateSize(prop,value)

% By default MaxSize/MinSize is [], and it can be set to empty too.
validateattributes( value,...
    {'numeric'}, {'real','nonsparse','finite','2d','integer','>=',0},...
    '',prop);

% Using 'vector',2 in validateattributes fails for [] so the
% following check makes sure that MaxSize has 2-elements
coder.internal.errorIf(~isempty(value) && (numel(value) ~= 2),...
    'vision:ObjectDetector:invalidSize',prop);
end

%=====
function flag = isSupportedModel(name)
    if (strcmpi(name, 'FrontalFaceCART') ...
        || strcmpi(name, 'FrontalFaceLBP') ...
        || strcmpi(name, 'ProfileFace') ...
        || strcmpi(name, 'Mouth') ...
        || strcmpi(name, 'Nose') ...
        || strcmpi(name, 'EyePairBig') ...
        || strcmpi(name, 'EyePairSmall') ...
        || strcmpi(name, 'RightEye') ...
        || strcmpi(name, 'LeftEye') ...
        || strcmpi(name, 'RightEyeCART') ...
        || strcmpi(name, 'LeftEyeCART') ...
        || strcmpi(name, 'UpperBody'))
        flag = true;
    else
        flag = false;
    end
end

```

```
end
end
```

```
%=====
function [isSupportedMdl, filename] = getFileName(name)
```

```
    if strcmpi(name, 'FrontalFaceCART')
        isSupportedMdl = true;
        filename = 'haarcascade_frontalface_alt2.xml';
    elseif strcmpi(name, 'FrontalFaceLBP')
        isSupportedMdl = true;
        filename = 'lbpcascade_frontalface.xml';
    elseif strcmpi(name, 'ProfileFace')
        isSupportedMdl = true;
        filename = 'haarcascade_profileface.xml';
    elseif strcmpi(name, 'Mouth')
        isSupportedMdl = true;
        filename = 'haarcascade_mcs_mouth.xml';
    elseif strcmpi(name, 'Nose')
        isSupportedMdl = true;
        filename = 'haarcascade_mcs_nose.xml';
    elseif strcmpi(name, 'EyePairBig')
        isSupportedMdl = true;
        filename = 'haarcascade_mcs_eyepair_big.xml';
    elseif strcmpi(name, 'EyePairSmall')
        isSupportedMdl = true;
        filename = 'haarcascade_mcs_eyepair_small.xml';
    elseif strcmpi(name, 'RightEye')
        isSupportedMdl = true;
        filename = 'haarcascade_mcs_righteye.xml';
    elseif strcmpi(name, 'LeftEye')
        isSupportedMdl = true;
        filename = 'haarcascade_mcs_lefteye.xml';
    elseif strcmpi(name, 'RightEyeCART')
        isSupportedMdl = true;
        filename = 'haarcascade_righteye_2splits.xml';
    elseif strcmpi(name, 'LeftEyeCART')
        isSupportedMdl = true;
        filename = 'haarcascade_lefteye_2splits.xml';
    elseif strcmpi(name, 'UpperBody')
        isSupportedMdl = true;
        filename = 'haarcascade_mcs_upperbody.xml';
    else
        isSupportedMdl = false;
        filename = '';
    end
end
```

```
%=====
function flag = isSimMode()
    flag = isempty(coder.target);
end
```